



---

## My script worked in CIAO 2.3. Why won't it work in CIAO 3?

---

A significant change between CIAO 2.3 and CIAO 3 is that as of CIAO 3.0, *Sherpa* converts all input data to double precision, and performs all its computations in double precision. A script that defines values as `Float_Type` was appropriate for CIAO 2.3, but has a bad effect in CIAO 3. Changing those values to `Double_Type` should yield the expected results.

---

The Chandra X-Ray Center (CXC) is operated for NASA by the Smithsonian Astrophysical Observatory.  
60 Garden Street, Cambridge, MA 02138 USA.  
Smithsonian Institution, Copyright © 1998–2006. All rights reserved.

URL:  
[http://cxc.harvard.edu/ciao3.4/faq/slang\\_ciao23.html](http://cxc.harvard.edu/ciao3.4/faq/slang_ciao23.html)  
Last modified: 26 October 2007

## FAQ Entry – CIAO 3.4