



AHELP for CIAO 3.4

chips_clear

Context: [chips](#)*Jump to:* [Description](#) [Examples](#) [Bugs](#) [See Also](#)

Synopsis

Removes all plotting objects, creating a new blank drawing area.

Syntax

```
chips_clear()
```

Description

This is a S-Lang version of the ChIPS CLEAR command. It erases all curves, lines, labels, and resets the number of panes (i.e. drawing areas) to 1. Since it has no parameters, it can be called without the "()".

Example 1

```
chips> chips_clear
```

Clear ChIPS of all plotting objects.

Example 2

```
() = chips_clear;
```

As the first example, but done in a S-Lang script.

Bugs

See the [bugs page for ChIPS](#) on the CIAO website for an up-to-date listing of known bugs.

See Also

chips

[chips auto redraw](#), [chips color name](#), [chips color value](#), [chips get pane](#), [chips get xrange](#), [chips get xscale](#), [chips get yrange](#), [chips get yscale](#), [chips get zrange](#), [chips get zscale](#), [chips label](#), [chips line](#), [chips pickpoints](#), [chips redraw](#), [chips set pane](#), [chips set xrange](#),

Ahelp: chips_clear – CIAO 3.4

[chips_set_xscale](#), [chips_set_yrange](#), [chips_set_yscale](#), [chips_set_zrange](#), [chips_set_zscale](#),
[chips_split](#), [chips_version](#)

The Chandra X-Ray Center (CXC) is operated for NASA by the Smithsonian
Astrophysical Observatory.
60 Garden Street, Cambridge, MA 02138 USA.
Smithsonian Institution, Copyright © 1998–2006. All rights reserved.

URL:
http://cxc.harvard.edu/ciao3.4/chips_clear.html
Last modified: December 2006